

# Release Notes IPC serie NEIUS

**1099/562**

## **NVSS\_V13.6.2.20210602\_SP21**

File STEP1: TC-C35SN-I3-E\_16MFlash\_OEM  
\_NVSS\_V13.6.2.20210602\_uboot\_kernel\_filesystem.box (aggiornando con questo file la versione della Telecamera passa da **V13.6.1.20210602** a **V13.6.2.20210602**)

File STEP2: TC-C35SN-I3-E\_16MFlash\_OEM\_NVSS\_V13.6.2.20210602\_SP1.box  
(aggiornando con questo file la versione della Telecamera passa da **V13.6.2.20210602** a **V13.6.2.20210602\_SP21**)

### **ITALIAN**

**IMPORTANTE:** procedere con l'aggiornamento locale tramite la pagina web della telecamera oppure utilizzando il software *SearchConfig Tool V2.0* dopo aver scaricato il file di aggiornamento firmware dalla sezione **DOWNLOAD - FIRMWARE** del sito [neius.urmet.com](http://neius.urmet.com).

#### **Modifiche STEP1(V13.6.2.20210602):**

1. Aggiornato ActiveX "NetVideo.exe"
2. Aggiunto supporto autenticazione Digest&Basic per RTSP e HTTP
3. Rimossa opzione CGI di accesso piattaforma
4. Correzione di alcune stringhe

#### **Modifiche STEP2(V13.6.2.20210602\_SP1):**

1. Risolto problema del mancato funzionamento dei comandi di zoom e fuoco utilizzando l'app Urmet NEIUS.

### **ENGLISH**

File STEP1: TC-C35SN-I3-E\_16MFlash\_OEM  
\_NVSS\_V13.6.2.20210602\_uboot\_kernel\_filesystem.box (updating with this file the version of the Camera goes from **V13.6.1.20210602** to **V13.6.2.20210602**)

File STEP2: TC-C35SN-I3-E\_16MFlash\_OEM\_NVSS\_V13.6.2.20210602\_SP1.box  
(updating with this file the version of the Camera goes from **V13.6.2.20210602** to **V13.6.2.20210602\_SP1**)

**IMPORTANT:** download the update files from the **DOWNLOAD - FIRMWARE** section of the website [neius.urmet.com](http://neius.urmet.com), then proceed with the local update either via the usual webpage of the device or with the software *SearchConfig Tool V2.0*.

**STEP1 Changes (V13.6.2.20210602):**

1. Updated ActiveX "NetVideo.exe"
2. Added Digest&Basic authentication support for RTSP and HTTP
3. Removed platform login CGI option
4. Fixed some strings

**STEP2 Changes (V13.6.2.20210602\_SP1):**

1. Fixed zoom and focus controls not working when using the Urmet NEIUS app.